

Criação de ODBC


Sybase 12

Para criação e/ou configuração do ODBC.


- **Windows Versão 32bits**

1. O usuário deve clicar em Iniciar --> Painel de controle --> Ferramentas administrativas --> ODBC(fontes de dados) ou Abrir o Windows explorer e ir na pasta C:\windows e localizar o arquivo ODBCAD32.EXE. Será aberta a tela abaixo.


1.



2. O usuário deve clicar na aba SYSTEM DSN ou Fontes de Dados de Sistema.
3. Na aba SYSTEM DSN ou Fontes de Dados de sistema, clicar em ADD ou adicionar.
4. Deve ser selecionado o driver Sybase Sql Anywhere 12 e clique em Finish ou concluir.




5. Preencher a tela conforme figuras abaixo.
O campo Data Source Name deve ser preenchido preferencialmente com o nome da empresa.



The screenshot shows the 'Advanced' tab of the 'ODBC Configuration for SQL Anywhere' dialog box. The 'Data source name' field is filled with 'SUPORTE12'. Below it are empty fields for 'Description' and 'Isolation level'. There are several unchecked checkboxes: 'Microsoft applications (Keys in SQLStatistics)', 'Delphi applications', 'Suppress fetch warnings', 'Prevent driver not capable errors', and 'Delay AutoCommit until statement close'. The 'Describe Cursor Behavior' section has three radio buttons: 'Never', 'If required' (which is selected), and 'Always'. At the bottom right is a 'Test Connection' button, and at the bottom center are 'OK', 'Cancelar', and 'Ajuda' buttons.

O campo Server Name deve ser preenchido preferencialmente com o do Banco de Dados da empresa.



The screenshot shows the 'Login' tab of the 'ODBC Configuration for SQL Anywhere' dialog box. The 'Authentication' dropdown is set to 'Database'. The 'User ID' field contains 'BYTEC' and the 'Password' field contains six dots. There is an unchecked checkbox for 'Encrypt password'. The 'Action' dropdown is set to 'Connect to a running database on another computer'. Below are empty fields for 'Host', 'Port', and 'Database name'. The 'Server name' field contains 'SUPORTE12'. At the bottom are 'OK', 'Cancelar', and 'Ajuda' buttons.